Server upgrade from version 7.8 to version 8.0.

This guide applies to upgrading from version 7.8 to version 8 server (64-bit), where the databases are hosted on a SQL Server. The 32-bit version follows the same upgrade process.

The upgrade must be performed from the location where the Febdok server was originally installed. You cannot upgrade the Febdok server from a Febdok client. Before starting Febdok after the upgrade, you must upgrade the SQL database. The screenshots in this guide are taken from Windows 10.

To upgrade from version 7.8 to version 8, you need to know whether you are using the 32-bit or 64-bit version. You must use the same type during the upgrade. You cannot upgrade from 32-bit to 64-bit or vice versa.

NB! Both the server and the clients must be upgraded. It is recommended to uninstall the clients before starting the server upgrade.

Download version 8 from our website: www.febdok.no.




Figure 1 Choose "Engelsk" to get the installation in English.



Figure 2 Click "Next".




Figure 3 Select Organization

You should select NHO Elektro if your business is located in Norway.

If you have a license from one of our partners in Sweden, Denmark, or Finland, you can select them as your organization.

- NHO Elektro applies to Norway
- AEC Sverige applies to Sweden
- AEC Danmark applies to Denmark
- Sähköinfo applies to Finland



Figure 4 You must accept the Febdok end user agreement to install the program.

If you did not read the agreement during installation, you can find it in the Febdok directory on your PC afterward, if you wish to read it.

It is located in the Febdok folder on the server, under the subfolder: \Extra\LisensDoc.




Figure 5 Select a destination folder (UNC-path)

Select the folder on the server where the Febdok program is installed.

If you're unsure, you can open a file named FebdokInstallDir.txt located in the ClientSetup folder. Copy the exec path from the first backslash.

Example: \\servername\foldername




Figure 6 Click "Install" to install the program.




Figure 7 Click "Finish" to complete the installation/upgrade of Febdok.



Figure 8 Run Febdok and log in.



First-time login for a user in Febdok.

The first time you log in as a user in this version of Febdok, you must accept the End User License Agreement. This only needs to be done once per user.

If you do not accept the agreement, you will not be able to use the program.




Figure 8 Log in with the user for the first time




Figure 9 You must accept this End User License Agreement.



Figure 10 After the agreement is accepted, you will enter the program.